riseRFM95 Documentation

The RFM95Communication class enables communication over LoRa using the RFM95 module. It provides methods for sending and receiving data using LoRa.

Constructor

```
RFM95Communication(uint8_t address)
```

The constructor takes one argument address which is the address of the device. The address is used to distinguish between devices in a LoRa network.

Public Methods

```
void setup()
```

The setup method initializes the RFM95 module and sets the LoRa parameters such as frequency, spreading factor, bandwidth, and coding rate.

```
void send(uint8_t toAddress, const SensorReading& reading)
```

The <u>send</u> method takes two arguments: <u>toAddress</u> and <u>reading</u>. <u>toAddress</u> specifies the address of the device to which the data is being sent. <u>reading</u> is a <u>sensorReading</u> struct that contains the data to be sent.

The method encrypts the data using AES-256 and uses the CSMA/CA algorithm to avoid collisions with other devices on the LoRa network. It waits for a random time interval and checks if the channel is clear before transmitting the packet.

```
bool receive(SensorReading& reading, uint8_t& fromAddress, uint8_t desiredAddress)
```

The receive method takes three arguments: reading, fromAddress, and desiredAddress. reading is a sensorReading struct that contains the received data. fromAddress is the address of the device from which the data was received. desiredAddress is the address of the device that is intended to receive the data.

The method waits for a random time interval and checks if there is any data available on the channel. If there is data available, it decrypts the data using AES-256 and copies it to the reading struct. If the data is intended for the device (desiredAddress matches the device's address), it returns true. If there is no data available, it checks if the channel is clear. If the channel is clear, it returns false.

Private Variables

uint8_t address_

The address variable is the address of the device.

```
RH_RF95 rf95_
```

The rf95_ variable is an instance of the RH_RF95 class, which is used to communicate with the RFM95 module.

```
uint8_t receiveBuffer_[RH_RF95_MAX_MESSAGE_LEN]
```

The receiveBuffer variable is a buffer that is used to receive data from the LoRa network.

```
byte key[32] and byte iv[32]
```

The key and iv variables are used to encrypt and decrypt the data using AES-256. The key is a 256-bit key and the iv is a 128-bit initialization vector.

Example:

```
#include <RiseTelemetry.h>
RFM95Communication rfm95Communication(MY_ADDRESS);
void setup() {
 Serial.begin(9600);
  rfm95Communication.setup();
void loop() {
  // Create a sensor reading to send
 SensorReading reading;
 reading.temperature = 25;
 reading.humidity = 50;
 reading.lightLevel = 1000;
 rfm95Communication.send(OTHER_ADDRESS, reading);
 delay(1000);
  // this struct will be updated to be the received struct
 SensorReading receivedReading;
  // after the receive function this uint_8 will contain the address of the sender of the received packet
 uint8_t fromAddress;
 if (rfm95Communication.receive(receivedReading, fromAddress, OTHER_ADDRESS)) {
    Serial.print("Received sensor reading from address ");
    Serial.print(fromAddress);
    Serial.print(": ");
    Serial.print(receivedReading.temperature);
    Serial.print(" ");
    Serial.print(receivedReading.humidity);
    Serial.print(" ");
    Serial.println(receivedReading.lightLevel);
 }
}
```

riseRFM95 Documentation 2

riseRFM95 Documentation 3